

Annexure 1 – DR Connection parameters of BOLT Plus Trading system for Equity Derivatives segment

Trading members can connect to the DR site of BOLT Plus trading system using either BOLT TWS or 3rd party trading application of empanelled vendors or in-house developed systems through IML exe ver.7.0 & above or ETI APIs as follows –

1. BOLT TWS Users

Trading members shall have to change the technical connection parameters in the configuration settings window at the time of login. Configuration settings window can be invoked using the scrip profile icon or “Shift+F12” shortcut keys on BOLT TWS.

Configuration Settings X

Connectivity Mode

Production ▼

Interactive Leased Line Internet

Broadcast Leased Line Internet Direct ▼

Masters Leased Line Internet

IP Settings (View / Edit)

Leased Line Internet

Segment	Production		Disaster Recovery	
	IP	Port	IP	Port
Eq/Derv				
IP 1	10 . 255 . 255 . 6	12908	10 . 255 . 241 . 10	12908
IP 2	10 . 255 . 255 . 7	12908	10 . 255 . 241 . 11	12908
Eq MCast IP	227 . 0 . 0 . 21	12996	Mcast IP/Port Same as Production	
Derv MCast IP	227 . 0 . 0 . 22	12997	Mcast IP/Port Same as Production	
Commodity				
IP 1	10 . 255 . 255 . 12	14908	10 . 255 . 241 . 10	14908
IP 2	10 . 255 . 255 . 13	14908	10 . 255 . 241 . 11	14908
MCastIP	228 . 0 . 0 . 22	14996	Mcast IP/Port Same as Production	
Currency				
IP 1	10 . 255 . 255 . 12	10408	10 . 255 . 241 . 10	10908
IP 2	10 . 255 . 255 . 13	10908	10 . 255 . 241 . 11	10908
MCastIP	229 . 0 . 0 . 21	10996	Mcast IP/Port Same as Production	
Extranet IP	10 . 1 . 101 . 108		10 . 1 . 101 . 213	

General Settings

IML Port 6001

Admin Trade CSV File /Feed Format with Deal Code Broadcast Logging

Other Settings

Market Report Frequency 6 x 10 Sec

Market Information Update Frequency Medium ▼


Scrip Id / Name Display

Equity <input checked="" type="radio"/> Scrip Id <input type="radio"/> Scrip Name	Derivative <input checked="" type="radio"/> Scrip Id <input type="radio"/> Scrip Name
--	--

Change
Save
Cancel

2. 3rd party trading application through IML or ETI APIs

- i. Connecting through IML exe – members shall have to change the technical connection parameters in the IML configuration settings window at the time of login.



Configuration Setting			
Connection Preference			
<input checked="" type="radio"/> BOLTplus		<input type="radio"/> BOLTplus and BOLT	
Member Settings			
Member Id	1	Trader Id	1
BOLTplus Host Side (Interactive and Broadcast)			
Host IP	10.255.255.13	Port No	11908
Alt Host IP	10.255.255.12	Alt Port No	11908
DR Host IP	10.255.241.11	DR Port No	11908
DR Alt Host IP	10.255.241.10	DR Alt Port No	11908
Host Multicast IP 1	228.0.0.21	UDP Host Port 1	11996
Host MultiCast IP 2		UDP Host Port 2	
BOLT Host Side (Interactive)			
Host IP	10.1.101.93	Port No	2349
Alt Host IP	10.1.101.94	Alt Port No	2349
TPS Side / Current Settings			
TPS Port No.	6001	Interface IP	10.228.61.13
UDP Address 1	0	UDP Port 1	0
UDP Address 2	0	UDP Port 2	0
Change		Save	
Cancel		Close	

- ii. Connecting through ETI – members shall have to change the technical connection parameters in their respective trading application as follows –

Primary DR – IP: 10.255.241.11; Port: 11908

Secondary DR – IP: 10.255.241.10; Port: 11908

****End of Document****