


Annexure 1 – DR Connection parameters of BOLT Plus Trading system for Currency Derivatives segment

Trading members can connect to the DR site of BOLT Plus trading system using either BOLT TWS or 3rd party trading application of empanelled vendors or in-house developed systems through IML exe ver.7.0 & above or ETI APIs as follows –

1. BOLT TWS Users

Trading members shall have to change the technical connection parameters in the configuration settings window at the time of login. Configuration settings window can be invoked using the scrip profile icon or “Shift+F12” shortcut keys on BOLT TWS.



Configuration Settings

Connectivity Mode

Production

Interactive ☒ Leased Line ☐ Internet

Broadcast ☒ Leased Line ☐ Internet

Masters ☒ Leased Line ☐ Internet

Direct

IP Settings (View / Edit)

☒ Leased Line ☐ Internet

Segment	Production	Port	Disaster Recovery	Port
Eq/Derv	10 . 255 . 255 . 6	12908	10 . 255 . 241 . 10	12908
IP 1	10 . 255 . 255 . 7	12908	10 . 255 . 241 . 11	12908
IP 2	227 . 0 . 0 . 21	12996	Mcast IP/Port Same as Production	
Eq MCast IP	227 . 0 . 0 . 22	12997	Mcast IP/Port Same as Production	
Derv MCast IP				

Commodity	Production	Port	Disaster Recovery	Port
IP 1	10 . 255 . 255 . 12	14908	10 . 255 . 241 . 10	14908
IP 2	10 . 255 . 255 . 13	14908	10 . 255 . 241 . 11	14908
MCastIP	228 . 0 . 0 . 22	14996	Mcast IP/Port Same as Production	

Currency	Production	Port	Disaster Recovery	Port
IP 1	10 . 255 . 255 . 12	10408	10 . 255 . 241 . 10	10908
IP 2	10 . 255 . 255 . 13	10908	10 . 255 . 241 . 11	10908
MCastIP	229 . 0 . 0 . 21	10996	Mcast IP/Port Same as Production	

Extranet IP

10 . 1 . 101 . 108

10 . 1 . 101 . 213

General Settings

IML Port 6001

☐ Admin Trade CSV File /Feed Format with Deal Code ☐ Broadcast Logging

Other Settings

Market Report Frequency 6 x 10 Sec

Market Information Update Frequency Medium

Scrip Id / Name Display


Equity ☒ Scrip Id ☐ Scrip Name

Derivative ☒ Scrip Id ☐ Scrip Name

Change Save Cancel

2. 3rd party trading application through IML or ETI APIs

- i. Connecting through IML exe – members shall have to change the technical connection parameters in the IML configuration settings window at the time of login.



Configuration Setting

Connection Preference
☒ BOLTplus ☐ BOLTplus and BOLT

Member Settings
 Member Id: 1 Trader Id: 1

BOLTplus Host Side (Interactive and Broadcast)
 Host IP: 10.255.255.12 Port No: 10908
 Alt Host IP: 10.255.255.13 Alt Port No: 10908
DR Host IP: 10.255.241.10 DR Port No: 10908
DR Alt Host IP: 10.255.241.11 DR Alt Port No: 10908
 Host MulticastIP 1: 229.0.0.21 UDP Host Port 1: 10996
 Host MultiCast IP 2: UDP Host Port 2:

BOLT Host Side (Interactive)
 Host IP: 10.1.101.93 Port No: 2349
 Alt Host IP: 10.1.101.94 Alt Port No: 2349

TPS Side / Current Settings
 TPS Port No.: 6001 Interface IP: 10.228.61.13
 UDP Address 1: 0 UDP Port 1: 0
 UDP Address 2: 0 UDP Port 2: 0

Change Save Cancel Close

- ii. Connecting through ETI – members shall have to change the technical connection parameters in their respective trading application as follows –

Primary DR – IP: 10.255.241.10; Port: 10908

Secondary DR – IP: 10.255.241.11; Port: 10908

****End of Document****